



**USB PORT TO SERIAL PORT ADAPTER CABLE**  
**For Use with Edelbrock QwikData or EFI Systems,**  
**As Well As Other Data Acquisition or EFI Systems**  
**Catalog #91147**  
**INSTALLATION INSTRUCTIONS**

**PLEASE** study these instructions carefully before beginning this installation. If you have any questions, please call our **Technical Hotline at: 1-800-416-8628**, 7:00 am - 5:00 pm, Pacific Standard Time, Monday through Friday or e-mail us at [Edelbrock@Edelbrock.com](mailto:Edelbrock@Edelbrock.com).

**DESCRIPTION:** This is a USB to Serial communications adapter cable. It is used to convert a Laptop or PC USB port to a 9-pin RS232 serial communications connector. This item is included in all QwikData Data Acquisition and Edelbrock EFI kits. Software drivers are included on the supplied CD.

**KIT CONTENTS**

- 1 USB-to-Serial Adapter Cable

**SYSTEM REQUIREMENTS**

**Hardware** – A USB-enabled PC or Laptop

**Software** – Microsoft® Windows 98SE/ME/2000/XP



**INSTALLATION:** The drivers for the USB-Serial Port adapter cable are located on the supplied CD.

**Microsoft® Windows Installation**

Insert the disc into your CD-ROM drive and click on “*Install USB-to-DB9*” then follow the onscreen prompts.

**NOTE:** You may use the same program to un-install the driver if desired. Run the “*PL-2303 Driver Installer*” program again and follow the prompts to un-install the driver.

**TROUBLESHOOTING:** If the adapter is not communicating after installation of the driver, follow the troubleshooting suggestions below.

- Many serial devices will not operate on a COM port higher than 4. If the COM port is higher than 4, change it to a lower number using the Device Properties.
- To change the assigned COM number, go to the Start menu, click Control Panel then System. Select the Hardware tab and then Device Manager. Select the category “*Ports (COM & LPT)*” and right click the device “*USB-to-Serial (COM x)*” (Or a similar name. “*X*” represents the assigned COM number). Click the Port Settings tab, then the Advanced button. A box will be in the lower left corner to assign a different COM port to the adapter.

**NOTE:** This procedure applies only to Windows 98SE, ME, 2000, and XP.

**Edelbrock Corporation • 2700 California St. • Torrance, CA 90503**  
**Tech Line: 1-800-416-8628 • E-Mail: Edelbrock@Edelbrock.com**